

## Acceptance Testing

The MoToScope is run via MoT Commands in the following format:

:<Device ID (1 byte)><function command (1 byte) ><Arguments>

The semicolon specifies the start of a command. The device ID byte is equal to three (0x03) because it is the third device in the MoT admin device table. Each of the commands will also be followed by a checksum. This checksum can be calculated using the hex2MoTcmd.c script. Within this file, these checksums will be represented by XX. When creating your own commands, be sure to run the command inputs in the hex2MoTcmd.c script and append the checksum to your input command. More information about how to structure each command can be found in the user manual

The function byte is a number between 0 and 5 and maps to a specific functionality within the MoToScope.

## Initializing the scope

cmd string: :0300FD

## Modifying the scope

Changing the mode to scan through waveform monitoring mode cmd string: :030100FC

Changing the trigger delay to 0xFFFF cmd string: :030102FFFFFFC

Changing the trigger type to TIM2 cmd string: :030101FB

Changing the sample size to 0xFAFA cmd string: :030103FAFA05

Changing the report size to 0xABAB cmd string: :030104ABABA2

Changing the sample rate to 0xAAAA cmd string: :030105AAAAA3

## Running scan through waveform monitoring

Scan through start cmd string: :030200FB

Scan through stop cmd string: :030201FA

Scan through step cmd string: :030202F9

## Running repetitive waveform monitoring

Repetitive waveform monitoring cmd string: :0303FA

## Running single-shot waveform monitoring

Single-shot waveform monitoring cmd string: :0304F9